# Tech APP™



## **FEATURE UPDATE**

# **Version 2.1.1 Update**

Effective October 23rd, 2018, the Tech APP is updated to Version 2.1.1. The following features are available.

## **Features**

#### **XTLtouch Compatibility**

XTLtouch Panels are now available as an option in the **System Type** dropdown menu on the **System Information** screen. With Version 2.1.1, when viewing a list of systems for a customer, the XTLtouch system type has now been added to the list of available options to choose from.

#### **Improved Camera Support**

In System Information, when video is enabled, the maximum number of supported cameras has increased with Tech App 2.1.1. This change allows users to see up to 16 SecureCom Video $^{\text{\tiny M}}$  or Digital Watchdog $^{\text{\tiny M}}$  cameras when using the Virtual Keypad App $^{\text{\tiny M}}$  and VirtualKeypad.com. No updates to the app or website are required to enable this feature.

### **Hikvision™ NVR Support**

You can now add Hikvision NVR's through the Tech APP. When enabled in **System Information** under the **Third Party Integrations** tab and added in the **Video** section, the cameras can be viewed using the Virtual Keypad App™ and VirtualKeypad.com.

Follow the directions below to enable this feature:

- 1. On the Navigation Screen for the system, click the Edit icon next to the Software Version.
- 2. Scroll to the bottom of the page. Under **Third Party Integrations**, select the toggle to enable Hikvision integration. You will know you have enabled integration when the toggle is **Blue**.
- 3. Select the **Back Arrow** to go back to the **Navigation Screen**.
- 4. Select Video.
- 5. Next to Hikvision, select the + button.
- 6. Enter the Network Address, Username and Password for the NVR, and the HTTP and RTSP (Real Time Streaming Protocol) ports found under **NAT** in **Configuration Settings** of the NVR or via your network router if manually mapping ports.
- 7. Click Save.

#### **OpenEye<sup>™</sup> Support**

You can now enable the OpenEye integration through the Tech APP and view which OpenEye NVR's have been added to the system. Once enabled in **System Information** under the **Third Party Integration** tab, the NVR's can be connected and viewed using the Virtual Keypad  $App^{TM}$  and VirtualKeypad.com.