

Version 1.5.0 (7/25/25) Technical Update

SCS-VR™ software has been updated to Version 1.5.0 (7/25/25).

Password Parameters

This update allows Admin Users to configure the following password rules for users' passwords:

- Number of days the password is valid
- Minimum password length
- Required number of lower, upper, numeric, and/or special characters

Automation Connection

Previously, if the primary automation connection failed, heartbeat messages were delayed on the backup automation connection. Now, if the primary automation connection fails, the backup automation connection still receives heartbeat messages every 60 seconds.

S16 Messages

Previously, if the panel did not check in with the SCS-VR before its programmed Fail Time and the backup database was unavailable, S16 messages were not sent. This update allows S16 messages to send to the primary database, even when the backup database is unavailable.

Obtaining the New Firmware

Contact the Software Support Team in DMP Technical Support at 1.888.436.7832 for information on updating to SCS-VR Version 1.5.0 (7/25/25).