

734 Wiegand Interface Modules July 2012

Version 103 Software Update

Effective June 28, 2012, all 734 Wiegand Interface Modules are being manufactured with Version 103 (6/26/12) software. This version contains the following updated operation.

Updated Operation

Zone 3 REX

The following issue only occurred in the recently released Version 103 (4/23/12) software and only when Activate Zone 3 REX and Activate Zone 2 Bypass were programmed YES.

After the Zone 3 REX was tripped (short) activating the door relay, then the door (Zone 2) was opened automatically starting the Bypass timer, if the door wasn't closed before the end of the door relay time (typically 5 sec.) subsequent Zone 3 REX trips would not activate the door relay until the complete programmed Bypass time (typically 40 sec.) had expired. The REX operation couldn't occur because the Bypass timer was not correctly turned off when the door was closed.

If the door was closed before the end of the door relay time, the Bypass timer was correctly turned off and subsequent Zone 3 REX trips could occur properly.

Obtaining the New Software

To update to the latest software, return the 734 Wiegand Interface Module to DMP and simply indicate "Update to Latest Version Software" on the RMA tag. The Version 103 software can be loaded on hardware Level B or C 734 Modules. If you need RMA tags, contact DMP Customer Service at 1-800-641-4282.

REPAIR AUTHORIZATION

DO NOT SEND METAL CABINETS WITH CIRCUIT BOARD

157668

PRINT CLEARLY: THIS IS YOUR RETURN SHIPPING DOCUMENT.

Company ALAM C. NAME

Address ADDRESS

City _____ State _____ Zip _____

Model No. MODEL S/N _____

Installation Site _____

Describe Problem UPDATE TO LATEST SOFTWARE

Preferred return shipping method _____

FOR DMP USE ONLY

Received _____ By _____ Code _____

Bench Test _____ In-Circuit Test _____ Functional Test _____

Repaired _____ By _____ Code _____

Parts Replaced _____ By _____ Code _____

☒ PCB ☐ Housing ☐ Box ☐

Final Test _____ By _____

Shipped _____ By _____

Data Entry _____ By _____

KEEP THIS STUB FOR YOUR RECORDS

Repair Voucher

Model No. 157668 S/N _____

Installation Site _____

